


PHOTOSHOP® CS3 QUICK PRINT GUIDE (MAC)


1. Select “Print...” from the file drop down menu.



2. Select the printer being used from the drop down menu if it is not the default option.

3. Select “Page Setup” >

- A. “Format for:” > Select the printer to be used
- B. “Paper size” > Select appropriate paper size (Note: This is also where some printers’ print source is selected - i.e. Manual, Roll, Front Feeder, etc.)
- C. “Orientation” > Select appropriate portrait or landscape setting
- D. Select “OK” when finished



4. Under “Color Management” > “Options” >

- A. “Color Handling:” > Select “Photoshop Manages Colors”
- B. “Printer Profile:” > Select the relevant ICC profile for printer, paper & ink combination
- C. “Rendering Intent:” > Select “Perceptual”
- D. Uncheck “Black Point Compensation”
- E. Select “Print...” when finished

5. Under “Print” >

A. “Printer:” > If the printer used is not the default option, select it from the drop down menu.

B (i). Epson® Printers - Select the “Copies and pages” drop down menu>

I. “Print Settings” >



a. “Media Type” > Select recommended paper setting

b. “Mode” > “Advanced” > “Print Quality” > Select 1440 or 2880 dpi

c. Uncheck “High Speed”

d. Check “Finest Detail”

II. “Printer Color Management” > Select Off “(No Color Adjustment)”



B (ii). Other Printers - Under the “Copies and pages” drop down menu>

Other printers print setting menus vary (consult the manufacturers manual or help file) but main options to set:

- Select recommended media setting
- 1440 or 2880 dpi (or highest quality setting depending on preference)
- Turn off any printer color management
- Turn off any high speed option


6. Select “Print” when finished

FOR ADVANCED BLACK AND WHITE PHOTO MODE

1. In “Print...” >

2. Under “Color Management” >

A. “Color Handling” > Select “Printer Manages Colors” This turns off the printer profile so that it will not interfere with the Black & White advance mode.



3. Under “Print” >

A (a). Epson® Printers - Under the “Copies and pages” drop down menu

I. “Print Settings” >

a. “Color:” > Select “Advanced B&W Photo”

b. “Color To___ning:” > Select desired option

II. “Printer Color Management” > Modify settings for desired results

A (b). Other Printers - Under the “Copies and pages” drop down menu

- Consult manual or help file for advanced black and white printing options.

